


Main Screen



Menu Options Screen


This screen will allow you to jump ahead to any of the below screens.

This menu screen will display when the Menu Option Button is selected.

Menu Options Button


This button will provide easy access to all screens.

- Main Screen
- Individual Hood Status Screens
- Hood Summary
- System Check
- Tech Support Contact Information Screen
- Alarms & Alarm History
- Security
- General Maintenance Instructions
- Touch Screen User Guide




Hood Status (Individual Hood Selection) Screen

This screen will allow you to move to your choice of Individual Hood Status screen.



Individual Hood Status Screen

This screen will display all the information pertaining to each individual separately.



Hood Summary Screen

This screen shows the overall performance of the all hoods.

Main Screen **Hood Status** **Current Screen Hood Summary** **Alarms & Alarm History** **Tech Support Contact Info**

Main Screen **Hood Status** **Hood Summary** **Alarms** **Tech Support Contact Info**

Halton M.A.R.V.E.L. UV
DEMAND CONTROL VENTILATION

HOOD SUMMARY

Hood #	Hood Status	Hood CFM	Duct Temperature
Hood # H1	Off	0	0.0
Hood # H2	Off	0	0.0
Hood # H3	Off	0	0.0
Hood # H4	Off	0	0.0
Hood # H5	Off	0	0.0

Menu Options

Hood Status Hood CFM's Duct Temperature

System Check Screen

The System Check screen will be used by your service agent only.

Main Screen

Main Screen

Halton M.A.R.V.E.L. UV
DEMAND CONTROL VENTILATION

SYSTEM CHECK

Hood #	K Airflow	Damper Position %	Initiate Sys. Check	
Hood # H1	0.00	0	Check On	Off
Hood #H2	0.00	0	Exhaust Airflow	OK
Hood #H3	0.00	0	Fan Speed %	0
Hood #H4	0.00	0	SC Success	Failed
Hood #H5	0.00	0		

Menu Options

Alarms & Alarm History Screen

This screen will display your current alarms along with the alarm history.

Current Screen
Alarms & Alarm History

Main Screen Hood Status Hood Summary Alarms Tech Support Contact Info

Alarm Information
Time Alarm was Activated,
Alarm Description and Date

If text is Black – alarm is
current and not acknowledged

If text is Green – alarm is
not current and returned to
normal

If text is Red – alarm is
current and has been
acknowledged

ED 0

HH:MM:SS	HOOD 1 - ALARM " HI TEMPERATURE"DD/MM/YY
HH:MM:SS	HOOD 1 - ALARM " HI TEMPERATURE"DD/MM/YY
HH:MM:SS	HOOD 1 - ALARM " HI TEMPERATURE"DD/MM/YY

Menu Options

Technical Support Contact Information Screen

This screen provides our USA and Canadian phones numbers for technical help.

Main Screen Hood Status Hood Summary Alarms Tech Support Contact Info

Current Screen
Tech Support Contact Info

Halton M.A.R.V.E.L. UV
DEMAND CONTROL VENTILATION

For Technical Support Call:

USA 1-800-442-5866
Canada 1-800-565-2981

Menu Options

Security Features Screen

This screen will be used by your service agent only.

Main Screen

SECURITY FEATURES

Select a User and enter the password.
User Security level is displayed in the Current Access Class field.
Invalid password will set Password Error.

1 2 3

0

1
Selected User

Password Error
LB9000 - Click lamp to reset

Logout

0
Current Access Classes
(binary, class A is right-most digit)
LW6222

Menu Options

If you are a Halton Certified Service Agent that requires a password for the screen above, please contact Halton Service Network at 1(800)442-5866 (USA) or 1(800)565-2981.

Reset UV Hours

These screens is for Halton Certified Service Agents only. This screen will only be displayed once a password has been entered on the Security Feature screen.

Security Screen

Main Screen

RESET UV HOURS


Halton M.A.R.V.E.L. UV
DEMAND CONTROL VENTILATION

Hood #	Reset Total Hrs	Reset Clean Hrs
Hood # 1	Total Reset Hrs	Clean Reset Hrs
Hood # 2	Total reset Hrs	Clean Reset Hrs
Hood # 3	Total Reset Hrs	Clean Reset Hrs
Hood # 4	Total Reset Hrs	Clean Reset Hrs
Hood # 5	Total Reset Hrs	Clean Reset Hrs

Menu Options


General Maintenance Instructions

These screens will provide the general maintenance instructions for your system.



Touch Screen User Guide

These screens will give an overview of each screen and their functions.



Next/Previous Button

This button will take you to the user instructions for the next screen or the previous screen.